# TEKLYNX® LABEL MATRIX® VERSION®



LABEL DESIGN TUTORIAL





The information in this manual is not binding and may be modified without prior notice.

Supply of the software described in this manual is subject to a user license. The software may not be used, copied or reproduced on any medium whatsoever, except in accordance with this license.

No portion of this manual may be copied, reproduced or transmitted by any means whatsoever, for purposes other than the personal use of the buyer, unless written permission is obtained from **Braton Groupe sarl**.

© 2007 Braton Groupe sarl.

All rights reserved.

TEKLYNX and its products are trademarks or registered trademarks of Braton Groupe sarl or its affiliated companies. All other brands and product names are the trademarks of their respective owners.

Rev - 010607

### **Label Design Tutorial**

This tutorial walks you through the process of creating an employee name badge label that includes a company name, an employee name, a graphic, and a bar coded badge number. We will use the program's powerful database capabilities to access the employee name data from the Ex1.dbf sample database that is installed with the program. In addition, the badge number will be added as a bar code that can be scanned to track attendance at company events or for other purposes.

The following is a sample of the label we will create.




Figure 1 Name Badge Label

Note

The name badge label uses a predefined label format for an  $8.5 \times 11$  inch sheet of labels. For purposes of this exercise we will set up the label design to print to a Windows printer (like a laser or ink-jet printer). If you do not have this type of printer setup available you can still go through the basic label design steps covered in this exercise.

# Creating a New Label

1 Start the label design software.

The first time you launch the software, a message box will appear to inform you that a default printer was not found. If you see this message, click **OK** to start the Add Printer Wizard and set up your default printer.

2 From the introductory screen, select the Create a new label option, and then click OK.

The New Label Wizard appears.



Figure 2 New Label Wizard

- **3** On the first screen of the wizard, select the following two options:
  - Select a different printer for this design
  - Change the page size, set up margins, and/or print multiple labels per page
- 4 Click Next.



Figure 3 Select a Printer

- **5** Select a laser, ink-jet or dot matrix printer.
  - If necessary, you may need to first install the printer using Windows Control Panel.
- 6 Click Make this printer the "Specific Printer" for this label file..., and click Next.
- 7 Click One of the forms chosen below.
- **8** Click the **Form** drop-down list and select **Avery** as the form manufacturer.
- 9 Now click the bottom drop-down list and scroll down to select form 5395 - Name Badge - 2-1/3" X 3-3/8".
  - The preview on the left will change to show a page layout with two labels across and four labels down on the page.




Figure 4 Name Badge Form

#### 10 Click Next.

- 11 Continue clicking Next to accept the defaults for page size, margins, and number and size of labels per page.
- 12 The final screen of the wizard allows you to enter a description for your label. Type Employee badge with name and bar coded badge number in the Description box.

#### 13 Click Finish.

The selected label format appears in the design window.

- 14 On the File menu, click Save As.
- **15** Browse to save the label to your desktop and enter a file name (like **Employee Badge**), and then click **Save**.

#### Adding a Picture 1 On the Insert menu, click Picture.

The Picture Properties dialog box appears.




Figure 5 Picture Tab

- 2 In the Picture box, click Embedded.
- 3 Click File.

The Select Picture File dialog box appears.

4 Browse to the label design software's Sample Labels directory, select computer.pcx, and then click Open.

The path and file name of the picture appears, and the **Sample** area displays the selected image.

- 5 Click Place.
- **6** Position the cursor in the upper left corner of the label and click to place the image.



You can easily move the picture on the label by clicking once on the middle of the image and then dragging it to a new position using the mouse.




Figure 6 Add a Picture

The picture appears at its original size, which is too large for this label.

- **7** To make the picture smaller, position the cursor over the lower right corner image handle (one of the bars outlining the image), and click and drag it toward the upper left corner. Size the picture so it is about 3/4" high.
- 8 On the File menu, click Save.

# **Text Image**

Adding a Constant 1 On the Insert menu, click Text.

The **Text Properties** dialog box appears.

- 2 On the **Data** tab, click in the **Origin** box, and then click Constant as the data origin.
- 3 In the **Text** box, type **ABC Company**. Text appears in the **Sample** area as you type it.
- 4 Click the Font tab.




Figure 7 Font Tab

**5** Select the following font settings:

Font: Arial

Size: 24

Style: Regular

Note

If you are printing to a thermal or thermal-transfer printer, you should use a printer resident font instead of Arial.

- **6** Click **Place** and position the cursor near the top of the label, to the right of the picture.
- 7 Click the left mouse button to place the image. If necessary, you can click on the image and drag to move it.




Figure 8 Add Text

8 Save the label design.

#### Attaching a Database File

1 On the Insert menu, click Database File.

Alternatively, on the **File** menu, click **Label Properties**, click the **Database** tab, and click **Add**.

The Add Database Wizard appears.

- 2 Depending on the edition of the label design software you are using, you may be prompted to select the type of database setup to use. Select Normal Setup, and click Next.
- 3 Click File.

The **Select Database File** dialog box appears.



Figure 9 Select a Database File

**4** Browse to the label design software's **Sample Labels** directory, select **Ex1.dbf**, and then click **Open**.

The database file name you selected is displayed.

5 Click Next.

The label design software analyzes the database for the total number of records and for the field property information. When done, a list of fields in each record appears.




Figure 10 Database Field Information

6 Click Next.



Figure 11 Database Access Methods

- 7 Depending on the edition of the label design software you are using, you may be prompted to select a database access method. For purposes of this exercise, we will access the database beginning at the first record, so select Sequential access, and click Next.
- 8 In the Name box, type Employee Information.
- **9** Click **Finish** to complete the database setup.

The Ex1.dbf database is attached and its records can be accessed when adding a text, paragraph, bar code, or 2D bar code image to the label.

10 Save the label design.

# Adding Text with : a Database Origin

Adding Text with 1 On the Insert menu, click Text.

The **Text Properties** dialog box appears.

2 In the Origin box, click Database.

The Employee Information (Ex1.dbf) field information appears on the **Data** tab.




Figure 12 Database Data Origin

3 Select the fullname field.

4 Click the **Font** tab and select the following settings:

Font: Arial

Size: 14

Style: Regular

5 Click Place and click the left mouse button to place the text near the center of the label, slightly below the "ABC Company" text.




Figure 13 Add a Database Field

6 Save the label design.

# Adding a Bar Code 1 with a Counter Origin

Adding a Bar Code 1 On the Insert menu, click Bar Code.

The Bar Code Properties dialog box appears.

2 In the Origin box, click Counter.

The **Data** tab changes to display the Counter settings.




Figure 14 Counter Data Origin

**3** Select the following Counter settings:

Start At: 0001

Step By: 1

Sample: **0001** 

Base: Numbers

4 Click the Advanced button, set Keep Changes to Yes,

and then click OK.

5 Click on the Bar Code tab.




Figure 15 Bar Code Tab

**6** Select the following bar code settings:

Type: Extended 39

Density: 0.013 (Medium)

Text Where: Below

7 Click Place and click the left mouse button to place the bar code below the "fullname" database field.




Figure 16 Add a Bar Code

8 Save the label design.

#### Changing the Snap Value

- On the Tools menu, click Setup, and then click the View Settings tab.
- 2 In the **Snap Value** box, type **0.01**. (Decreasing the snap value makes it much easier to place an image at a specific point on the label.)
- 3 Click **OK** to return to the design window.

#### Positioning Images on the Label

- While pressing the SHIFT key, click once on the "fullname" field and once on the bar code.
- 2 With both images selected, click **Center Horizontally** on the Alignment Toolbar.
- 3 Save the label design.

Your label should now look something like this:




Figure 17 Final Name Badge Label

## **Printing**

Previewing Label 1 On the File menu, click Print Preview.

The **Print Preview** window appears, displaying a full page of labels.




Figure 18 Print Preview

Note

Depending on the edition of the software you are using, the Print Preview labels may display only sample data (low-end edition) or may display actual "live" data for the database records and counter values (mid-range and high-end editions).

Click **Close** to return to the design window.

# Design

**Printing the Label 1** On the **File** menu, click **Print**.

The **Print** dialog box appears.




Figure 19 Printing Options

- 2 Click Pages and leave the From and To settings at their defaults to print one page of labels.
- 3 Click **OK** to send the label to the printer.

One page of eight labels is printed.



United States Canada France Germany Singapore China Japan
1-414-535-6200 1-905-771-4104 33-562-601-080 49-6103-30026-0 65-6477-7293 86-21-6100-6588 81-45-461-3603